

Visualyse 7 Demo Installation Guide

System Requirements

Visualyse™ 7 should run on most newer PCs but the following table represents what Transfinite Systems considers to be the minimum and recommended system specifications.

	Minimum	Recommended
CPU	1.5 GHz	2.0+ GHz Dual Core
RAM	1 GB	2+ GB
Operating System	Microsoft Windows 2000/XP/Vista	Microsoft Windows XP
3D Graphics Card	3D Capable Video Card with 16 MB VRAM	3D Capable Video Card with 64+ MB VRAM
Hard Disk Space	300 MB	4+ GB
Display	1024*768, 32 bit true colour	1280*1024, 32 bit true colour

Microsoft Windows Vista

Whilst Visualyse™ 7 is supported on Microsoft Windows Vista it does not support the Aero graphical user interface so it will need to be disabled by following the steps below.

1. Right Click on the Vista desktop and select "Personalize".
2. Click on "Window Colour and Appearance".
3. Change the "Color Scheme" setting from "Windows Aero" to "Windows Vista Basic".
4. Click "OK".

Graphics Card

Visualyse™ 7 uses Open GL technology to greatly improve the graphical representation of the 2D and 3D maps. Graphics cards with small amounts of VRAM or graphics integrated on the motherboard of desktop and laptop PCs may result in an unacceptable Visualyse™ 7 user experience.

Prerequisites

Visualyse™ 7 uses XML technologies provided by the MSXML services from Microsoft. This must be installed so that Visualyse™ 7 can function correctly.

The install program is available from Microsoft at:

<http://www.microsoft.com/downloads/details.aspx?FamilyID=993c0bcf-3bcf-4009-be21-27e85e1857b1&displaylang=en>

Download and run the file msxml6.msi (the first file in the 'Files in This Download' section on this website).

Install Instructions

You will require "Administrator" privileges to install Visualyse™ 7 and either "Standard User" or "Administrator" privileges to run Visualyse™ 7.

1. Download the setup program from our website at:
http://www.transfinite.com/MaintenanceRelease/Visualyse_7_0_9_1_Install.zip
and save it on your PC's hard disk.
2. Run the setup program by unzipping the file and running Visualyse_7_0_9_1_Install.exe.
3. Follow the on screen instructions.

If you have any questions about the installation procedure, the software operation, Visualyse™ 7 new features or indeed any bugs please do not hesitate to contact us by email support@transfinite.com or by telephone +44 (0) 20 8240 6648